

Digifax Configuration

To install the hardware side of digifax:

1. From the prompt type # **swinstall**
 2. Choose **digifax 290a** (290a_auto is for a digifax card only)
Will you be able to reboot? Yes [hit the enter key]
 3. Fax Commands Installed [hit the enter key]
 4. There are 5 drivers, Answer no (n) to install any drivers
 5. Device name to modify; type (q) [hit the enter key]
 6. Device name to modify; type (q) [hit the enter key]
 7. Text Font Configuration [hit the enter key]
 8. After confirmed, type (y) [hit the enter key]
 9. Type (q) [hit the enter key]
 10. After confirmed, type (y) [hit the enter key]
 11. Type channel to modify, type (1) [hit the enter key]
 12. Choose (1) [hit the enter key]
 13. Type (efax) [hit the enter key]
 14. Choose (5) to disable receive, type (y) [hit the enter key]
 15. Choose (13) [hit the enter key]
 16. Type (a02) [hit the enter key]
 17. Choose (16) change company header [hit the enter key]
 18. Type (q) to quit [hit the enter key]
 19. Choose (18) [hit the enter key]
 20. Type (USR-Courier) [hit the enter key]
 21. Type (q) [hit the enter key]
 22. Type (q) [hit the enter key]
 23. Type (q) [hit the enter key]
 24. Make changes permanent, type (y) [hit the enter key]
 25. Confirm, type (y) [hit the enter key]
 26. Run faxconfig now, type (n) [hit the enter key]
 27. Type (I) to ignore errors [hit the enter key]
 28. Now reboot the system for changes to take affect.
- *Do Not program modem in digifax port or setup in modem list!!!!**

At # type sysut and enter. Arrow to printers and enter. Arrow to Software Printer Maintenance and enter. Hit the Ins key and enter the values listed below.

```

Printer Id code.....: Zfax
Description.....: Fax Document Software
Location.....: memory
[L]ocal/[R]emote/[T]ransparent: L
Printer type ([F7] for query): dumb
Forms class.....: fax
Device, file or |SpoolCommand.: /tmp/%temp
Command to execute before open:
Command to execute after close:fax_digi /tmp/%temp; rm -f /tmp/%temp

```

To save hit Ins and F10. Then Esc back to a #.

This fax printer will not work as a printer. Faxes are sent via the software. To ensure that the software uses the above setup printer do the following. At the # type clist and enter. Enter on the dataset you are using. Arrow to Point of Sale and enter. Arrow to Maintenance and enter. Arrow to Form and Printer Configuration and enter. Hit Ins to add the following.

```

*** CHANGE MODE ***
[Esc]-Abandon [Ins]-Save [F9]-Replicate
[PageUp]/[PageDown] scroll. Arrows and [Tab]/[Backtab] move cursor.
-----posforms 9904.80-2-----/work/hardtimes/userdata/-----12/19/2000-----
Workstation number: 2 Comment: normal
Standard POS forms
Delivery...: pos00001 Ptr: lp00
Invoices...: pos00001 Ptr: lp00
Quotes....: pos00001 Ptr: lp00
Estimates..: pos00001 Ptr: lp00
Cash sales.: pos00050 Ptr: lp00
Cash Drawer: pcd00001 Ptr: lp02
ROA receipt: roa00002 Ptr: lp00
Paid out...: Ptr:
Picking Tickets
Copy 1: pos00001 Ptr: lp00
Copy 2: pos00001 Ptr: lp00
Copy 3: pos00001 Ptr: lp00
Detail listings
Kit/BOM : Ptr: lp00
Bundle: Ptr: lp00
Installment agreements
Agreement: Ptr:
Special Forms
Display bar: pdbspl02 Ptr:
Credit card: Ptr:
Management Alert Reports
Credit hold: Ptr: lp00
Void ticket: pos00001 Ptr: lp00
Fax : pos00001 Ptr: Zfax
Notes Ptr: lp00
-----POS forms and printers configuration-----

```

Note: the workstation number should coincide with the number after the dash at the top left-hand corner of your screen. When finished Ins to save and you have now configured DigiFax.